


- 
-
- [Troubleshooting](#)
- PaperStream Connector Option Help



PaperStream Connector Option Help

PaperStream Connector Option is an optional product for saving scanned images to a cloud service or sending them by email or fax.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
-
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- Before Using This Help

Before Using This Help

Abbreviations Used in This Help

The abbreviations used in this help are as follows:

Abbreviations Used	Name
Google Chrome	Google Chrome™
Google Drive	Google Drive™

Conditions on Licenses for the Open Source Software

The open source software (OSS) is used in this help.

The following shows the OSS names, versions, and license names, which are used in this help.

No.	OSS Name	Version	License Name
1	jquery.biggerlink.js	2.0.1	MIT license
2	jquery.cookie.js	1.4.1	MIT license
3	jquery.highlight-4.js	4	MIT license

4	jquery.rcrumbs.js	1.1.0	MIT license
5	jquery.url.js	-	Unlicense
6	jquery-3.6.0.min.js	3.6.0	MIT license

Trademarks

Google, Google Chrome, and Google Drive are trademarks or registered trademarks of Google LLC.

Microsoft, OneDrive, and SharePoint are trademarks of the Microsoft group of companies.

PaperStream is a registered trademark or trademark of PFU Limited in Japan.

Other company names and product names are the registered trademarks or trademarks of the respective companies.

Issue Date/Issuer

Issue date: August 2023

Issued by: PFU Limited




Notice

- The contents of this help are subject to change without notice.
- PFU Limited assumes no liability for incidental or consequential damages arising from the use of this product, and any claims by a third party.
- Copying of the contents of this help, in whole or in part, as well as the scanner applications is prohibited under the copyright law.
- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



•

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [How to Use This Help](#)

How to Use This Help

This help is a manual that is to be referred to when you use PaperStream Connector Option.

Recommended Browsers

It is recommended that you use one of the browsers below to view and use this help properly.

- Google Chrome
- Microsoft Edge

ATTENTION

If an information bar is displayed when you view this help, follow the message that appears on the information bar and allow the blocked content.

To Search for Your Desired Topic with Keywords

Enter the keyword in the search bar that is located in the top of each topic, and click the [Search] button to display the topic titles in the search results.

AND Search

When you enter multiple keywords with a space between each word, the pages containing all the keywords that you entered are searched for.


Perfect Match Search

When the entered keywords are enclosed in double quotation marks, the pages containing all the keywords as a phrase are searched for.

Example: "PaperStream ClickScan"

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)



- 
- [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- Supported Products and Applicable Connectors

Supported Products and Applicable Connectors

This section explains the products supported by PaperStream Connector Option, the applicable connectors, and the system requirements.

Supported products

PaperStream Connector Option runs on the following applications:

- PaperStream Capture 3.6.0 or 3.9.0 or later
- PaperStream Capture Pro 3.6.0 or 3.9.0 or later
- PaperStream ClickScan 1.3.0 or later
- PaperStream NX Manager 2.2.0 or later

Applicable connectors

The applicable connectors will vary depending on the application.

Connector	PaperStream Capture PaperStream Capture Pro	PaperStream ClickScan	PaperStream NX Manager
Microsoft SharePoint Online	— (*1)	Yes	— (*2)
Dropbox (*3)	Yes	Yes	Yes
Send E-mail (*4)	Yes	Yes	— (*2)
Fax (*5)	Yes	Yes	Yes

Google Drive (*3)	Yes	Yes	Yes
Microsoft OneDrive (*3) (*6)	Yes	Yes	Yes

*1:

This function is provided by PaperStream Capture/PaperStream Capture Pro.

*2:

This function is provided by PaperStream NX Manager.

*3:

Shared drives and folders shared by other users cannot be specified as a save destination.

*4:

Used to directly connect to the SMTP server and send emails.

This is different from the existing email function (for linking with an email client application) in PaperStream Capture/PaperStream Capture Pro/PaperStream ClickScan.

*5:

You can use the Internet Fax service via the SMTP server.

Faxes will be sent in TIFF image (*.tif) format.

*6:

Microsoft OneDrive (for home use) and Microsoft OneDrive for Business are supported.


System requirements

Refer to the manual for each application.

Supported browser

- Google Chrome
- Microsoft Edge
- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

-

- 
- [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- Setting Destinations and Scanning Documents




Setting Destinations and Scanning Documents

Set an output destination for each application and scan documents.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Setting Destinations and Scanning Documents](#)>
- PaperStream Capture

PaperStream Capture

Set an output destination in PaperStream Capture to save images to a cloud service, send them by email, or send them by fax over the Internet.

1. Open the [Destination] tab in the [Configure Profiles] window.

The [Destination] tab is displayed.

2. Select the icon of the service being used as the [Destination] and click the [Settings] button.

The settings window for each service appears.

- [\[Dropbox\] Window](#)
- [\[Send E-mail\] Window](#)
- [\[Fax\] Window](#)
- [\[Google Drive\] Window](#)
- [\[Microsoft OneDrive\] Window](#)

3. Configure the destination settings and click the [OK] button.

You are returned to the [Destination] tab in the [Configure Profiles] window.

4. Configure settings such as the folder and file format in [File Properties].

ATTENTION

When using Microsoft OneDrive (for home use), the [Browse] button displayed after the [Name Rule] button for [Folder] is clicked may become slower to respond.

5. Click the [Save] button in the [Configure Profiles] window.
6. Click the [Close] button to close the [Configure Profiles] window.
7. Click [Back] in the menu.
8. Scan documents.




For details about how to scan documents, refer to the PaperStream Capture Help/PaperStream Capture Pro Help.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023




-

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#) >
- [Setting Destinations and Scanning Documents](#) >
- PaperStream ClickScan

PaperStream ClickScan

Set an output destination in PaperStream ClickScan to save images to a cloud service, send them by email, or send them by fax over the Internet.

1. In the setting scan parameters window, click  and select [Manage destinations].

The managing destinations window appears.

2. Click  or .

The adding destinations window or editing destinations window appears.

3. Select the icon of the service being used for the [Destination] and specify the items.

The settings window for each service appears.

- [Destination Window - \[Microsoft SharePoint Online\]](#)
- [Destination Window - \[Dropbox\]](#)
- [Destination Window - \[Send E-mail\]](#)
- [Destination Window - \[Fax\]](#)
- [Destination Window - \[Google Drive\]](#)
- [Destination Window - \[Microsoft OneDrive\]](#)

4. Click the [Save] button.

You are returned to the managing destinations window.

5. Click the [OK] button.

You are returned to the setting scan parameters window.

6. Scan documents.


For details about how to scan documents, refer to the PaperStream ClickScan Help.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



-

- 
- [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Setting Destinations and Scanning Documents](#)>
- PaperStream NX Manager

PaperStream NX Manager

Set an output destination in PaperStream NX Manager to save images to a cloud service or send them by fax over the Internet.

HINT

Web Scan does not support the connector option.

1. In the menu on the web page, click the [Connector] tab.

The [\[Connector Settings\] Window](#) appears.

2. In the [\[Connector Settings\] Window](#), configure and save the connector settings.
3. In the menu on the web page, click the [Job] tab and select the [Create New Job] window or the [Edit Job] window.
4. In the [Save Destination Settings in the \[Create New Job\] Window/\[Edit Job\] Window](#), select the connector you want to use for the save destination type. Then, specify each item for the selected connector and save the changes.

The window returns to the job list.



5. Scan documents.

For details about how to scan documents, refer to the "PaperStream NX Manager User's Guide".

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



- 
-
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- Windows



Windows

This section explains the settings window for each application.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
-
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- PaperStream Capture



PaperStream Capture

This section explains the windows used in PaperStream Capture.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
-
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream Capture](#)>
- [Dropbox] Window

[Dropbox] Window

Log in to Dropbox in this window.

[Login] button

Click this to log in to the service.

When you log in to the service, the login user name appears.

After you log in to the service, this button becomes the [Re-login] button.

ATTENTION

To log in to the service, use one of the following ports:

7217 to 7226

50000 to 50004

60000 to 60004

[OK] button

Applies the settings and closes the window.




[Cancel] button

Cancels the settings and closes the window.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream Capture](#)>
- [Send E-mail] Window

[Send E-mail] Window

Configure the settings for sending emails in this window.

SMTP Server

Set the SMTP server.

SMTP Server Port Number

Specify the port number of the SMTP server.

SSL

Select an SSL communication method from the drop-down list. The default value is [Off].

- [Off]
- [SSL on]
- [STARTTLS on]

[Server authentication required] check box

Select this check box when server authentication is required.

Username

Enter the user name for server authentication. This option becomes available when the [Server authentication required] check box is selected.

Password

Enter the password for server authentication. This option becomes available when the [Server authentication required] check box is selected.

Recipient's E-mail Address

Enter a recipient email address.

Multiple recipient email addresses can be entered by separating each email address with a line break.

Sender's E-mail Address

Enter a sender email address.

E-mail Subject

Enter an email subject.

Character Encoding

Select the encoding method for emails from the drop-down list.

- Automatic
- Unicode(UTF-8)

HINT

When [Automatic] is selected for [Character Encoding], character encoding for the message of an e-mail is automatically selected according to the system account language specified in the operating system.

The following shows languages and corresponding character encodings.

Language	Character Encoding
Arabic	ISO-8859-6
Italian	ISO-8859-1
Spanish	ISO-8859-1
German	ISO-8859-1
Turkish	ISO-8859-9
French	ISO-8859-1
Portuguese	ISO-8859-1
Russian	KOI8-R

English	US-ASCII
Korean	KS_C_5601-1987
Chinese (Simplified)	GB2312
Chinese (Traditional)	Big5
Japanese	ISO-2022-JP (JIS code)
Languages other than the ones listed above	US-ASCII

Attached File Size (MB)

Enter the maximum file size for files that can be attached to an email.

[OK] button

Applies the settings and closes the window.

[Cancel] button

Cancels the settings and closes the window.

Email body

The following information is output to the email body.

Item	Description
Subject	The specified email subject text is displayed.
First line	The following information is displayed. <ul style="list-style-type: none"> Name of the application being used for scanning PaperStream Capture/PaperStream Capture Pro Name of the computer being used to send emails Name of the file attached to the email
Date/time	Displays the date and time the email was sent.



Scanner model name	Displays the name of the scanner model which performed the scan.
User name	Displays the user name who performed the scan.
Batch name	Displays the batch name for the scan.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



-

- 
- 
- [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream Capture](#)>
- [Fax] Window

[Fax] Window

Configure the settings for sending faxes in this window.

You can use the Internet Fax service via the SMTP server.

SMTP Server

Set the SMTP server.

SMTP Server Port Number

Specify the port number of the SMTP server.

SSL

Select an SSL communication method from the drop-down list. The default value is [Off].

- [Off]
- [SSL on]
- [STARTTLS on]

[Server authentication required] check box

Select this check box when server authentication is required.

Username

Enter the user name for server authentication. This option becomes available when the [Server authentication required] check box is selected.

Password

Enter the password for server authentication. This option becomes available when the [Server authentication required] check box is selected.

Fax Domain

Enter the domain name of the Internet Fax service.

Fax No.

Enter the fax number.

Sender's Fax Address

Enter the email address of the user who makes a contract with the Internet Fax service.

Fax Subject

Enter the fax subject.

Character Encoding

Select the encoding method for emails (being sent to the Internet Fax service) from the drop-down list.

- Automatic
- Unicode(UTF-8)

HINT

When [Automatic] is selected for [Character Encoding], character encoding for the message of an email (being sent to the Internet Fax service) is automatically selected according to the system account language specified in the operating system.

The following shows languages and corresponding character encodings.

Language	Character Encoding
Arabic	ISO-8859-6
Italian	ISO-8859-1
Spanish	ISO-8859-1
German	ISO-8859-1
Turkish	ISO-8859-9
French	ISO-8859-1
Portuguese	ISO-8859-1

Russian	KOI8-R
English	US-ASCII
Korean	KS_C_5601-1987
Chinese (Simplified)	GB2312
Chinese (Traditional)	Big5
Japanese	ISO-2022-JP (JIS code)
Languages other than the ones listed above	US-ASCII

Attached File Size (MB)

Enter the maximum file size for files that can be attached to an email.

[OK] button

Applies the settings and closes the window.

[Cancel] button

Cancels the settings and closes the window.

Fax body

The following information is output to the fax body.

Item	Description
Subject	The specified fax subject text is displayed.
First line	<p>The following information is displayed.</p> <ul style="list-style-type: none"> Name of the application being used for scanning PaperStream Capture/PaperStream Capture Pro Name of the computer being used to send the fax Name of the file attached to the fax




Sender's Fax Address	Displays the fax sender's name (email address).
Date/time	Displays the date and time the fax was sent.
Scanner model name	Displays the name of the scanner model which performed the scan.
User name	Displays the user name who performed the scan.
Batch name	Displays the batch name for the scan.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



-

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream Capture](#)>
- [Google Drive] Window

[Google Drive] Window

Log in to Google Drive in this window.

[Login] button

Click this to log in to the service.

When you log in to the service, the login user name appears.

After you log in to the service, this button becomes the [Re-login] button.

ATTENTION

To log in to the service, use one of the following ports:

7217 to 7226

50000 to 50004

60000 to 60004

Destination folder URL

Enter a URL and choose where to save it.

[OK] button


Applies the settings and closes the window.

[Cancel] button

Cancels the settings and closes the window.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)



- 
- [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream Capture](#)>
- [Microsoft OneDrive] Window

[Microsoft OneDrive] Window

Log in to Microsoft OneDrive in this window.

[Login] button

Click this to log in to the service.

When you log in to the service, the login user name appears.

After you log in to the service, this button becomes the [Re-login] button.

ATTENTION

To log in to the service, use one of the following ports:

7217 to 7226

50000 to 50004

60000 to 60004

[OK] button

Applies the settings and closes the window.



[Cancel] button

Cancels the settings and closes the window.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
-
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- PaperStream ClickScan




PaperStream ClickScan

This section explains the windows used in PaperStream ClickScan.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream ClickScan](#)>
- Destination Window - [Microsoft SharePoint Online]

Destination Window - [Microsoft SharePoint Online]

Add [Microsoft SharePoint Online] as the destination for scanned images.

Destination information

Destination name

Enter a destination name.

Destination

Select [Microsoft SharePoint Online].

Destination settings

Site URL

Specify the URL for Microsoft SharePoint Online.

[Sign in with multi-factor authentication on the browser] check box

Select this check box to display the browser and sign in with authentication.

Click the [Connect] button to display the browser and enter the required sign in information.

User name

Specify a user name for signing in to Microsoft SharePoint Online.

You can enter a user name when the [Sign in with multi-factor authentication on the browser] check box is cleared.

When you are signed in with the [Sign in with multi-factor authentication on the browser] check box selected, the account used to sign in is displayed.

Password

Specify a password for signing in to Microsoft SharePoint Online.

You can enter a password when the [Sign in with multi-factor authentication on the browser] check box is cleared.

To establish a connection for the account with multi-factor authentication using an app password, enter the account name in [User Name] and the app password in [Password].

[Sign out] button

This is displayed when you are signed in on the browser used for authentication.

Deletes the user information used to sign in.

[Connect] button

Connects to the specified URL and signs in to the site with the specified user name and password.

When the [Sign in with multi-factor authentication on the browser] check box is selected, a sign in window for authentication is displayed on the browser.

If a connection is established, libraries for the site are displayed in the [Library] drop-down list.

Library

Select a library for the site from the drop-down list.

Folder

Shows the folder that was selected in the window displayed when the [Browse] button was clicked.

[Browse] button

Click this button, and in the [\[Folder settings\] Window](#) that appears, select a destination folder.

File to be output

File naming method

From the drop-down list, select a naming rule for image files that are to be output.

For details, refer to the PaperStream ClickScan Help.

[Save to folder] check box

Save the scanned images to a folder on a computer.

When this check box is selected, the following input field appears.

Destination folder

Enter the full path of a folder where scanned images are to be saved.

[Browse] button

Click this button, and in the window that appears, select a destination folder.

Quality check

[Show preview edit screen] check box

Select this check box to display the preview window.

Clear this check box to output scanned images to a destination without displaying the preview window.



Displays this Help.

[Save] button

Applies the settings and closes the window.

[Cancel] button



Cancels the settings and closes the window.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



•

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream ClickScan](#)>
- Destination Window - [Dropbox]

Destination Window - [Dropbox]

Add [Dropbox] as the destination for scanned images.

Destination information

Destination name

Enter a destination name.

Destination

Select [Dropbox].

Destination settings

[Login] button

Click this to log in to the service.

When you log in to the service, the login user name appears.

After you log in to the service, this button becomes the [Re-login] button.

ATTENTION

To log in to the service, use one of the following ports:

7217 to 7226

50000 to 50004

60000 to 60004

Folder

Shows the folder that was selected in the window displayed when the [Browse] button was clicked.

[Browse] button

Click this button, and in the [\[Folder settings\] Window](#) that appears, select a destination folder.

File to be output

File naming method

From the drop-down list, select a naming rule for image files that are to be output.

For details, refer to the PaperStream ClickScan Help.

[Save to folder] check box

Save the scanned images to a folder on a computer.

When this check box is selected, the following input field appears.

Destination folder

Enter the full path of a folder where scanned images are to be saved.

[Browse] button

Click this button, and in the window that appears, select a destination folder.

Quality check

[Show preview edit screen] check box

Select this check box to display the preview window.

Clear this check box to output scanned images to a destination without displaying the preview window.



Displays this Help.

[Save] button

Applies the settings and closes the window.

[Cancel] button




Cancels the settings and closes the window.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



•

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream ClickScan](#)>
- Destination Window - [Send E-mail]

Destination Window - [Send E-mail]

Add [Send E-mail] as the destination for scanned images.

Destination information

Destination name

Enter a destination name.

Destination

Select [Send E-mail].

Destination settings

SMTP Server

Set the SMTP server.

SMTP Server Port Number

Specify the port number of the SMTP server.

SSL

Select an SSL communication method from the drop-down list. The default value is [Off].

- [Off]
- [SSL on]
- [STARTTLS on]

[Server authentication required] check box

Select this check box when server authentication is required.

Username

Enter the user name for server authentication. This option becomes available when the [Server authentication required] check box is selected.

Password

Enter the password for server authentication. This option becomes available when the [Server authentication required] check box is selected.

Recipient's E-mail Address

Enter a recipient email address.

Multiple recipient email addresses can be entered by separating each email address with a line break.

Sender's E-mail Address

Enter a sender email address.

E-mail Subject

Enter an email subject.

Character Encoding

Select the encoding method for emails from the drop-down list.

- Automatic
- Unicode(UTF-8)

HINT

When [Automatic] is selected for [Character Encoding], character encoding for the message of an e-mail is automatically selected according to the system account language specified in the operating system.

The following shows languages and corresponding character encodings.

Language	Character Encoding
Arabic	ISO-8859-6
Italian	ISO-8859-1
Spanish	ISO-8859-1
German	ISO-8859-1

Turkish	ISO-8859-9
French	ISO-8859-1
Portuguese	ISO-8859-1
Russian	KOI8-R
English	US-ASCII
Korean	KS_C_5601-1987
Chinese (Simplified)	GB2312
Chinese (Traditional)	Big5
Japanese	ISO-2022-JP (JIS code)
Languages other than the ones listed above	US-ASCII

Attached File Size (MB)

Enter the maximum file size for files that can be attached to an email.

File to be output

File naming method

From the drop-down list, select a naming rule for image files that are to be output.

For details, refer to the PaperStream ClickScan Help.

[Save to folder] check box

Save the scanned images to a folder on a computer.

When this check box is selected, the following input field appears.

Destination folder

Enter the full path of a folder where scanned images are to be saved.

[Browse] button

Click this button, and in the window that appears, select a destination folder.

Quality check

[Show preview edit screen] check box

Select this check box to display the preview window.

Clear this check box to output scanned images to a destination without displaying the preview window.



Displays this Help.

[OK] button

Applies the settings and closes the window.

[Cancel] button

Cancels the settings and closes the window.

Email body

The following information is output to the email body.




Item	Description
Subject	The specified email subject text is displayed.
First line	The following information is displayed. <ul style="list-style-type: none"> Name of the application being used for scanning PaperStream ClickScan Name of the computer being used to send emails Name of the file attached to the email
Date/time	Displays the date and time the email was sent.
Scanner model name	Displays the name of the scanner model which performed the scan.
User name	Displays the user name who performed the scan.

Destination name	Displays the name of the destination for the scan.
------------------	--

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream ClickScan](#)>
- Destination Window - [Fax]

Destination Window - [Fax]

Add [Fax] as the destination for scanned images.

Destination information

Destination name

Enter a destination name.

Destination

Select [Fax].

Destination settings

SMTP Server

Set the SMTP server.

SMTP Server Port Number

Specify the port number of the SMTP server.

SSL

Select an SSL communication method from the drop-down list. The default value is [Off].

- [Off]
- [SSL on]
- [STARTTLS on]

[Server authentication required] check box

Select this check box when server authentication is required.

Username

Enter the user name for server authentication. This option becomes available when the [Server authentication required] check box is selected.

Password

Enter the password for server authentication. This option becomes available when the [Server authentication required] check box is selected.

Fax Domain

Enter the domain name of the Internet Fax service.

Fax No.

Enter the fax number.

Sender's Fax Address

Enter the email address of the user who makes a contract with the Internet Fax service.

Fax Subject

Enter the fax subject.

Character Encoding

Select the encoding method for emails (being sent to the Internet Fax service) from the drop-down list.

- Automatic
- Unicode(UTF-8)

HINT

When [Automatic] is selected for [Character Encoding], character encoding for the message of an email (being sent to the Internet Fax service) is automatically selected according to the system account language specified in the operating system.

The following shows languages and corresponding character encodings.

Language	Character Encoding
Arabic	ISO-8859-6
Italian	ISO-8859-1
Spanish	ISO-8859-1
German	ISO-8859-1

Turkish	ISO-8859-9
French	ISO-8859-1
Portuguese	ISO-8859-1
Russian	KOI8-R
English	US-ASCII
Korean	KS_C_5601-1987
Chinese (Simplified)	GB2312
Chinese (Traditional)	Big5
Japanese	ISO-2022-JP (JIS code)
Languages other than the ones listed above	US-ASCII

Attached File Size (MB)

Enter the maximum file size for files that can be attached to an email.

File to be output

File naming method

From the drop-down list, select a naming rule for image files that are to be output.

For details, refer to the PaperStream ClickScan Help.

[Save to folder] check box

Save the scanned images to a folder on a computer.

When this check box is selected, the following input field appears.

Destination folder

Enter the full path of a folder where scanned images are to be saved.

[Browse] button

Click this button, and in the window that appears, select a destination folder.

Quality check

[Show preview edit screen] check box

Select this check box to display the preview window.

Clear this check box to output scanned images to a destination without displaying the preview window.



Displays this Help.

[OK] button

Applies the settings and closes the window.

[Cancel] button

Cancels the settings and closes the window.

Fax body

The following information is output to the fax body.

Item	Description
Subject	The specified fax subject text is displayed.
First line	The following information is displayed. <ul style="list-style-type: none"> Name of the application being used for scanning PaperStream ClickScan Name of the computer being used to send the fax Name of the file attached to the fax
Sender's Fax Address	Displays the fax sender's name (email address).
Date/time	Displays the date and time the fax was sent.
Scanner model name	Displays the name of the scanner model which performed the scan.




User name	Displays the user name who performed the scan.
Destination name	Displays the name of the destination for the scan.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



-

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream ClickScan](#)>
- Destination Window - [Google Drive]

Destination Window - [Google Drive]

Add [Google Drive] as the destination for scanned images.

Destination information

Destination name

Enter a destination name.

Destination

Select [Google Drive].

Destination settings

[Login] button

Click this to log in to the service.

When you log in to the service, the login user name appears.

After you log in to the service, this button becomes the [Re-login] button.

ATTENTION

To log in to the service, use one of the following ports:

7217 to 7226

50000 to 50004

60000 to 60004

Destination folder URL

Enter a URL and choose where to save it.

File to be output

File naming method

From the drop-down list, select a naming rule for image files that are to be output.

For details, refer to the PaperStream ClickScan Help.

[Save to folder] check box

Save the scanned images to a folder on a computer.

When this check box is selected, the following input field appears.

Destination folder

Enter the full path of a folder where scanned images are to be saved.

[Browse] button

Click this button, and in the window that appears, select a destination folder.

Quality check

[Show preview edit screen] check box

Select this check box to display the preview window.

Clear this check box to output scanned images to a destination without displaying the preview window.



Displays this Help.

[Save] button

Applies the settings and closes the window.

[Cancel] button




Cancels the settings and closes the window.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



•

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream ClickScan](#)>
- Destination Window - [Microsoft OneDrive]

Destination Window - [Microsoft OneDrive]

Add [Microsoft OneDrive] as the destination for scanned images.

Destination information

Destination name

Enter a destination name.

Destination

Select [Microsoft OneDrive].

Destination settings

[Login] button

Click this to log in to the service.

When you log in to the service, the login user name appears.

After you log in to the service, this button becomes the [Re-login] button.

ATTENTION

To log in to the service, use one of the following ports:

7217 to 7226

50000 to 50004

60000 to 60004

Folder

Shows the folder that was selected in the window displayed when the [Browse] button was clicked.

[Browse] button

Click this button, and in the [\[Folder settings\] Window](#) that appears, select a destination folder.

ATTENTION

When using Microsoft OneDrive (for home use), the [Browse] button may become slower to respond.

File to be output

File naming method

From the drop-down list, select a naming rule for image files that are to be output.

For details, refer to the PaperStream ClickScan Help.

[Save to folder] check box

Save the scanned images to a folder on a computer.

When this check box is selected, the following input field appears.

Destination folder

Enter the full path of a folder where scanned images are to be saved.

[Browse] button

Click this button, and in the window that appears, select a destination folder.

Quality check

[Show preview edit screen] check box

Select this check box to display the preview window.

Clear this check box to output scanned images to a destination without displaying the preview window.



Displays this Help.

[Save] button




Applies the settings and closes the window.

[Cancel] button

Cancels the settings and closes the window.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)



- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- PaperStream NX Manager




PaperStream NX Manager

This section explains the windows used in PaperStream NX Manager.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream NX Manager](#)>
- [Connector Settings] Window

[Connector Settings] Window

Set the connector information in this window.

Dropbox

Displayed when the Dropbox connector is installed.

Refer to [Authentication Client Settings for Dropbox](#) and obtain the setting values required for connection in advance.

Client ID

Enter the Dropbox client ID.

Client secret

Enter the Dropbox client secret.

Redirect URI

Enter the Dropbox redirect URI.

[Copy] button

The redirect URI is copied to a clipboard.

Fax

Displayed when the fax connector is installed.

SMTP Server

Specify the SMTP server for sending faxes.

SMTP Server Port Number

Enter the port number for the SMTP server being used to send faxes. The default values are as follows:

- When [SSL] is set to [Off]: 25
- When [SSL] is set to [SSL on]: 465
- When [SSL] is set to [STARTTLS on]: 587

SSL

Select an SSL communication method from the drop-down list. The default value is [Off].

- [Off]
- [SSL on]
- [STARTTLS on]

[Server authentication required] check box

Select this check box when server authentication is required. If [SMTP Server] is not specified, authentication information will not be saved.

Username

Enter the user name for server authentication. This option becomes available when the [Server authentication required] check box is selected.

Password

Enter the password for server authentication. This option becomes available when the [Server authentication required] check box is selected.

Fax Domain

Enter the domain name of the Internet Fax service.

Sender's Fax Address

Enter the email address of the user who makes a contract with the Internet Fax service.

Attached File Size (MB)

Enter the maximum file size for files that can be attached to an email.

Google Drive

Displayed when the Google Drive connector is installed.

Refer to [Authentication Client Settings for Google Drive](#) and obtain the setting values required for connection in advance.

Client ID

Enter the Google Drive client ID.

Client secret

Enter the Google Drive client secret.

Redirect URI

Enter the Google Drive redirect URI.

[Copy] button

The redirect URI is copied to a clipboard.

Microsoft OneDrive

Displayed when the Microsoft OneDrive connector is installed.

Refer to [Authentication Client Settings for Microsoft OneDrive](#) and obtain the setting values required for connection in advance.

Client ID

Enter the Microsoft OneDrive client ID.

Client secret

Enter the Microsoft OneDrive client secret.

Redirect URI

Enter the Microsoft OneDrive redirect URI.

[Copy] button

The redirect URI is copied to a clipboard.

[Save] button

Saves the connector settings.




If you switch tabs without clicking the [Save] button, the settings are not saved.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



•

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [PaperStream NX Manager](#)>
- Save Destination Settings in the [Create New Job] Window/[Edit Job] Window

Save Destination Settings in the [Create New Job] Window/[Edit Job] Window

Set save destinations for each connector in this window.

This section is about the items in the window when Dropbox, Fax, Google Drive, or Microsoft OneDrive is selected for the save destination type.

When a type other than the above is selected, refer to the "PaperStream NX Manager User's Guide".

HINT

If Dropbox, Google Drive, or Microsoft OneDrive is selected for [Type] of the save destination, the [Browser Settings] and [Scanner Communication Settings] in the [Preferences] window are available for the selected connector.

Save Destination

If connectors are installed, you can configure the detailed settings for the connector you want to use.

Type

Select the connector you want to use from the drop-down list. The connectors that can be selected are as follows:

- Dropbox
- Fax
- Google Drive
- Microsoft OneDrive

When Dropbox, Google Drive, or Microsoft OneDrive is selected for [Type]

The following items are displayed.

[Enable proxy] check box

Select this check box to use the proxy server specified in [Network Settings] in the [Preferences] tab.

Service

Click the [Login] button to log in to the service selected in [Type].

When you log in to the service, the login user name appears.

After you log in to the service, this button becomes the [Re-login] button.

Folder

Specify a folder for the save destination selected in [Type].

[Browse] button

Click this button, and in the [\[Folder settings\] Window](#) that appears, select a destination folder.

ATTENTION

When using Microsoft OneDrive (for home use), the [Browse] button may become slower to respond.

[Overwrite if the same file name already exists] check box

Select this check box to overwrite the existing file if a file with the same name already exists in the destination folder.

When Fax is selected for [Type]

The following items are displayed.

Fax No.

Enter the fax number.

Fax Subject

Enter the fax subject.

Character Encoding

Select the encoding method for emails (being sent to the Internet Fax service) from the drop-down list.

- Automatic
- Unicode(UTF-8)

HINT

When [Automatic] is selected for [Character Encoding], character encoding for the message of an email (being sent to the Internet Fax service) is automatically selected according to the system account language specified in the operating system.

The following shows languages and corresponding character encodings.

Language	Character Encoding
Arabic	ISO-8859-6
Italian	ISO-8859-1
Spanish	ISO-8859-1
German	ISO-8859-1
Turkish	ISO-8859-9
French	ISO-8859-1
Portuguese	ISO-8859-1
Russian	KOI8-R
English	US-ASCII
Korean	KS_C_5601-1987
Chinese (Simplified)	GB2312
Chinese (Traditional)	Big5
Japanese	ISO-2022-JP (JIS code)
Languages other than the ones listed above	US-ASCII

[Save] button

Saves the settings.

If you switch tabs without clicking the [Save] button, the settings are not saved.

Fax body

The following information is output to the fax body.



Item	Description
Subject	The specified fax subject text is displayed.
First line	The following information is displayed. <ul style="list-style-type: none"> • Name of the application used for scanning: PaperStream NX Manager • Name of the computer being used to send the fax • Name of the file attached to the fax
Sender's Fax Address	Displays the fax sender's name (email address).
Date/time	Displays the date and time the fax was sent.
Scanner model name	Displays the name of the scanner model which performed the scan.
Scanner name	Displays the name of the scanner which performed the scan.
Serial number	Displays the serial number of the scanner which performed the scan.
User name	Displays the user name who performed the scan.
Job name	Displays the job name for the scan.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



•

- 
-
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- Common Windows


Common Windows

This section explains the windows commonly displayed in each application.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
- [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Windows](#)>
- [Common Windows](#)>
- [Folder settings] Window

[Folder settings] Window

In this window, specify a folder to which to output the scanned images.

ATTENTION

Note that some folders may not be displayed for Microsoft OneDrive. If the desired folder is not displayed, manually enter the folder path.

HINT

A destination folder including / or \ can be created in the Google Drive service. To specify a folder including / or \ as a destination folder, create the folder in advance and select it from [Select a folder].

Select a folder

Click this to select a destination folder.

[OK] button

Applies the settings and closes the window.



[Cancel] button

Cancel the settings and closes the window.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
-
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- Troubleshooting




Troubleshooting

The solutions for troubles that may occur when PaperStream Connector Option is in use are described in this section.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Troubleshooting](#)>
- A Message Indicating That a Fax Was Sent Successfully Is Displayed When No Fax Was Actually Sent

A Message Indicating That a Fax Was Sent Successfully Is Displayed When No Fax Was Actually Sent

Cause

Possible causes are:

- The specified fax domain does not exist
- The specified fax number does not exist
- The specified fax sender does not exist
- An unsupported image file format was specified


Solution

Check the following, edit the specified value, and then send the fax again.

- Error emails sent from the Internet Fax service to a contractant
- Console of the Internet Fax service
- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
- [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Troubleshooting](#)>
- Error Messages

Error Messages

The causes and the solutions for errors are described in this section.

- The "XXXXXX" in an error code varies depending on the connector being used.
- (*) is added to the messages that appear only in the PaperStream NX Manager window.

Error code	Message
PSXXXXXX2001	Some required items have not been specified. (<ItemName>)
PSXXXXXX2002	Incorrect format specified. (<ItemName>)
PSXXXXXX2003	Maximum length exceeded. (<ItemName>)
PSXXXXXX2005	The specified file does not exist. (<FilePath>)
PSXXXXXX2006	The specified folder already exists. (<FolderPath>)
PSXXXXXX2007	The specified file already exists. (<FilePath>)
PSXXXXXX2008	You need to specify a file.
PSXXXXXX2009	You need to specify a folder.

PSXXXXXX2101	PaperStream Connector Option is not installed.
PSXXXXXX2101 (*)	An error occurred. Possible causes are: - Temporary internal error. Press the [F5] key to refresh the window. - PaperStream Connector Option has been uninstalled. Install PaperStream Connector Option again.
PSXXXXXX2102	Unsupported connector.
PSXXXXXX2103	Unsupported method.
PSXXXXXX2104, PSXXXXXX3110	The client ID/client secret may be incorrect. Check the setting items and try again.
PSXXXXXX2105, PSXXXXXX2106	You have not logged in to the service.
PSXXXXXX2107	Detected that a file(s) with a file size larger than the specified size was/were released.
PSXXXXXX2108	Enter a correct folder name.
PSXXXXXX2109	No destination folder is specified.
PSXXXXXX2110	No redirect URI is specified.
PSXXXXXX2112	Unsupported image file format.
PSXXXXXX3001 to PSXXXXXX3003, PSXXXXXX3122 to PSXXXXXX3125	An internal error occurred. Details: <Message>
PSXXXXXX3004	An error occurred during communication. Details: <Message>
PSXXXXXX3011	The proxy settings are incorrect. Check the setting items and try again.

PSXXXXXX3012	Request timed out. Try again later.
PSXXXXXX3013	Failed to connect to the specified folder. The computer may not be connected to the network. (<FolderPath>)
PSXXXXXX3014	Failed to authenticate the specified folder. The username or password is incorrect. (<FolderPath>)
PSXXXXXX3015	Access to the specified folder is not permitted. (<FolderPath>)
PSXXXXXX3101, PSXXXXXX3102, PSXXXXXX3108	Login to the service failed. Check the setting items and try again.
PSXXXXXX3103	An invalid client ID was specified. Check the authentication information and try again.
PSXXXXXX3104	An invalid client secret was specified. Check the authentication information and try again.
PSXXXXXX3105, PSXXXXXX3106	Login to the service failed. Check the redirect URI and try again.
PSXXXXXX3107	Login to the service failed. Incorrect scope. Change the settings and try again.
PSXXXXXX3109	Logout failed. Try again later.
PSXXXXXX3111, PSXXXXXX3112, PSXXXXXX3127	Failed to obtain the folder. Check the setting items and try again after a while.
PSXXXXXX3113, PSXXXXXX3117	Failed to obtain the information of the user logged in to the service. Check the settings and try again.

PSXXXXXX3114	Failed to create a folder. Details: <Message>
PSXXXXXX3115	File upload failed. Check the setting items and try again after a while.
PSXXXXXX3116	The size of the file you tried to save is too large. Divide the documents and scan again.
PSXXXXXX3119, PSXXXXXX3128	Failed to obtain the destination list. Check the setting items and try again after a while.
PSXXXXXX3120, PSXXXXXX3121	You have automatically logged out of the linked service because there was no operation for a certain period of time. Log in to the service again.
PSXXXXXX3126	Out of scope. Grant the requested scope and try the login again.
PSXXXXXX3129	The total file size has reached the maximum storage capacity of the linked service. Delete unnecessary files and try again.
PSXXXXXX3130, PSXXXXXX3131	Failed to send an e-mail. Details: <Message>
PSXXXXXX3132, PSXXXXXX3138	Failed to send a fax. Details: <Message>
PSXXXXXX3133	Failed to connect to the SMTP server. Check the settings and try again.
PSXXXXXX3134	The e-mail address settings are invalid. Check the setting items, and then retry the operation.
PSXXXXXX3135	The port number is invalid. Check the setting items and try again.
PSXXXXXX3136	The file name is too long. Check the setting items and try again.
PSXXXXXX3137	You do not have an access permission. Check the authentication settings and

	try again.
PSXXXXXX3139	Failed to create a folder. Details: <Message>
PSXXXXXX3140	File upload failed. Details: <Message>
PSXXXXXX3141	Failed to obtain the folder. Details: <Message>
PSXXXXXX3142	The number of requests has exceeded the request rate limit. Try again later. Details: <Message>
PSXXXXXX3144	Failed to delete the file. Check the setting items and try again after a while.
PSXXXXXX3145	Failed to delete the file. Details: {0}
PSXXXXXX3146	An unsupported extension is selected. ({0})
-	No URL is configured for the file destination in Microsoft SharePoint Server.
-	No user name for Microsoft SharePoint Server is specified.
-	No password for Microsoft SharePoint Server is specified.
-	Failed to connect to Microsoft SharePoint Server.
-	No library name for Microsoft SharePoint Server is specified.
-	Failed to upload document(s) to Microsoft SharePoint Server.
-	The folder for Microsoft SharePoint Server has not been specified.

Some required items have not been specified. (<ItemName>)

Cause

Some required items have not been specified.

Solution

Check the corresponding items and specify them.

Incorrect format specified. (<ItemName>)

Cause

The incorrect format is specified.

Solution

Change the format specified for the corresponding item and try again.

Maximum length exceeded. (<ItemName>)

Cause

Maximum length exceeded.

Solution

Change the length specified for the corresponding item and try again.

The specified folder does not exist. (<FolderPath>)

Cause

The specified folder does not exist.

Solution

Make sure that the specified folder exists and then again.

The specified file does not exist. (<FilePath>)

Cause

The specified file does not exist.

Solution

Make sure that the specified file exists and try again.

The specified folder already exists. (<FolderPath>)

Cause

The specified folder already exists.

Solution

Change the folder name and try again.

The specified file already exists. (<FilePath>)

Cause

The specified file already exists.

Solution

Perform one of the following and try again.

- Save the file with another name
- Overwrite the existing file

You need to specify a file.

Cause

No file is specified.

Solution

Specify a file and try again.

You need to specify a folder.

Cause

No folder is specified.

Solution

Specify a folder and try again.

PaperStream Connector Option is not installed.

Cause

PaperStream Connector Option is not installed.

Solution

Reload the window. If the problem persists, uninstall and reinstall PaperStream Connector Option.

An error occurred. Possible causes are: - Temporary internal error. Press the [F5] key to refresh the window. - PaperStream Connector Option has been uninstalled. Install PaperStream Connector Option again.

Cause

- Temporary internal error.
- PaperStream Connector Option has been uninstalled.

Solution

- Press the [F5] key to refresh the window.
- Install PaperStream Connector Option again.

Unsupported connector.

Cause

Unsupported connector.

Solution

Make sure that PaperStream NX Manager is correctly installed and try again.

If the problem still persists, take note of the operation procedure which you took when the error occurred, the displayed error code/error message, and contact the distributor/dealer where you purchased this product.

Unsupported method.

Cause

Unsupported method.

Solution

Make sure that PaperStream NX Manager is correctly installed and try again.

If the problem still persists, take note of the operation procedure which you took when the error occurred, the displayed error code/error message, and contact the distributor/dealer where you purchased this product.

The client ID/client secret may be incorrect. Check the setting items and try again.

Cause

The client ID or client secret may be incorrect.

Solution

Check the values entered for the client ID and client secret and try again.

You have not logged in to the service.

Cause

You have not logged in to the service.

Solution

Log in to the service.

Detected that a file(s) with a file size larger than the specified size was/were released.

Cause

A file(s) with a file size larger than the specified size was/were released.

Solution

Perform the following, and try again.

- Increase the value of the file size setting
- Change the scan settings in the setting scan parameters window in order to reduce the size of files to be output
- Scan the documents in batches and release the scanned images

Enter a correct folder name.

Cause

The folder name is incorrect.

Solution

Change the folder name and try again.

No destination folder is specified.

Cause

No destination folder is specified.

Solution

Specify a destination folder and try again.

No redirect URI is specified.

Cause

No redirect URI is specified.

Solution

Specify a value and try again.

Unsupported image file format.

Cause

Unsupported image file format.

Solution

Make sure that the image file format is supported and try again.

An internal error occurred. Details: <Message>

Cause

An internal error occurred.

Solution

Check the setting items and try again after a while.

If the problem still persists, take note of the operation procedure which you took when the error occurred, the displayed error code/error message, and contact the distributor/dealer where you purchased this product.

An error occurred during communication. Details: <Message>

Cause

An error occurred during communication.

Solution

Refer to the details, check the connection status, and try again later.

The proxy settings are incorrect. Check the setting items and try again.

Cause

The proxy settings are incorrect.

Solution

Check the proxy settings and try again.

Request timed out. Try again later.

Cause

Time-out occurred.

Solution

Check your network environment and try again after a while.

Failed to connect to the specified folder. The computer may not be connected to the network. (<FolderPath>)

Cause

The computer may not be connected to the network.

Solution

Check the connection status of the network and try again.

Failed to authenticate the specified folder. The username or password is incorrect. (<FolderPath>)

Cause

The username or password is incorrect.

Solution

Change the username or password and try again.

Access to the specified folder is not permitted. (<FolderPath>)

Cause

Access to the specified folder is not permitted.

Solution

Check the access permission for the folder, allow access to the folder if necessary, and try again.

Login to the service failed. Check the setting items and try again.

Cause

Login to the service failed.

Solution

Check the setting items and try again.

An invalid client ID was specified. Check the authentication information and try again.

Cause

An invalid client ID was specified.

Solution

Check the setting items and try again.

An invalid client secret was specified. Check the authentication information and try again.

Cause

An invalid client secret was specified.

Solution

Check the setting items and try again.

Login to the service failed. Check the redirect URI and try again.

Cause

Login to the service failed.

Solution

Make changes to the setting items for the redirect URI and try again.

Login to the service failed. Incorrect scope. Change the settings and try again.

Cause

Login to the service failed.

Solution

Grant the requested scope and try again.

Logout failed. Try again later.

Cause

Logout failed.

Solution

Try again later.

Failed to obtain the folder. Check the setting items and try again after a while.

Cause

An error occurred while attempting to obtain the folder.

Solution

Check the setting items and try again after a while.

Failed to obtain the information of the user logged in to the service. Check the settings and try again.

Cause

An error occurred while attempting to obtain the user information.

Solution

Check the setting items and try again after a while.

Failed to create a folder. Details: <Message>

Cause

Failed to create a folder.

Solution

Check the setting items and try again after a while.

File upload failed. Check the setting items and try again after a while.

Cause

File upload failed.

Solution

Check the setting items and try again after a while.

The size of the file you tried to save is too large. Divide the documents and scan again.

Cause

The file size has exceeded the maximum size that can be uploaded.

Solution

Perform one of the following and try again.

- Change the scan settings in the setting scan parameters window in order to reduce the size of image files to be output
- Scan the documents in batches and release the scanned images

Failed to obtain the destination list. Check the setting items and try again after a while.

Cause

Failed to obtain the destination list.

Solution

Check the setting items and try again after a while.

You have automatically logged out of the linked service because there was no operation for a certain period of time. Log in to the service again.

Cause

You have automatically logged out of the linked service because there was no operation for a certain period of time.

Solution

In the setting window for the following connectors, click the [Re-login] button to log back in to the service.

- Dropbox
- Google Drive
- Microsoft OneDrive

Out of scope. Grant the requested scope and try the login again.

Cause

Failed to log in to the service due to insufficient scope.

Solution

Grant the requested scope and try the login again.

For details about the scope settings, refer to [Appendix](#).

The total file size has reached the maximum storage capacity of the linked service. Delete unnecessary files and try again.

Cause

The total file size has reached the maximum storage capacity of the linked service.

Solution

Delete unnecessary files in the linked service and try again.

Failed to send an e-mail. Details: <Message>

Cause

Failed to send an e-mail.

Solution

Check the details and try again.

If the problem still persists, take note of the operation procedure which you took when the error occurred, the displayed error code/error message, and contact the distributor/dealer where you purchased this product.

Failed to send a fax. Details: <Message>

Cause

Failed to send a fax.

Solution

Check the details and try again.

If the problem still persists, take note of the operation procedure which you took when the error occurred, the displayed error code/error message, and contact the distributor/dealer where you purchased this product.

Failed to connect to the SMTP server. Check the settings and try again.

Cause

Failed to connect to the SMTP server.

Solution

Check the setting items and try again.

The e-mail address settings are invalid. Check the setting items, and then retry the operation.

Cause

The email address is in an invalid format or the maximum number of specified addresses has been reached.

Solution

Check the email addresses and try again.

The port number is invalid. Check the setting items and try again.

Cause

The port number is invalid.

Solution

Check the port number and try again.

The file name is too long. Check the setting items and try again.

Cause

The file name is too long.

Solution

The file name can be up to 260 characters long.

Shorten the file name and try again.

You do not have an access permission. Check the authentication settings and try again.

Cause

You do not have an access permission.

Solution

Check the authentication settings and try again.

Failed to create a folder. Details: <Message>

Cause

Failed to create a folder.

Solution

Check the details and try again.

If the problem still persists, take note of the operation procedure which you took when the error occurred, the displayed error code/error message, and contact the distributor/dealer where you purchased this product.

File upload failed. Details: <Message>

Cause

File upload failed.

Solution

Check the details and try again.

If the problem still persists, take note of the operation procedure which you took when the error occurred, the displayed error code/error message, and contact the distributor/dealer where you purchased this product.

Failed to obtain the folder. Details: <Message>

Cause

Failed to obtain the folder.

Solution

Check the details and try again.

If the problem still persists, take note of the operation procedure which you took when the error occurred, the displayed error code/error message, and contact the distributor/dealer where you purchased this product.

The number of requests has exceeded the request rate limit. Try again later. Details: <Message>

Cause

Too many requests or writing operations have been performed in a few minutes.

Solution

Try again later.

Failed to delete the file. Check the setting items and try again after a while.

Cause

Failed to delete the file.

Solution

Check the setting items and try again after a while.

Failed to delete the file. Details: {0}

Cause

Failed to delete the file.

Solution

Check the setting items and try again after a while.

If the problem still persists, take note of the operation procedure which you took when the error occurred, the displayed error code/error message, and contact the distributor/dealer where you purchased this product.

An unsupported extension is selected. ({0})

Cause

Unsupported extension.

Solution

Change the file format for images to be output.

No URL is configured for the file destination in Microsoft SharePoint Server.

Cause

The URL of the Microsoft SharePoint site is not specified.

Solution

Enter the URL of the Microsoft SharePoint site that you want to connect to in [Site URL] in [Destination settings].

No user name for Microsoft SharePoint Server is specified.

Cause

The user name that is used to sign in to Microsoft SharePoint is not specified.

Solution

Enter the user name that is used to sign in to Microsoft SharePoint in [User Name] in [Destination settings].

No password for Microsoft SharePoint Server is specified.

Cause

The password that is used to sign in to Microsoft SharePoint is not specified.

Solution

Enter the password that is used to sign in to Microsoft SharePoint in [Password] in [Destination settings].

Failed to connect to Microsoft SharePoint Server.

Cause

It was not possible to connect to the specified site URL.

Solution

Make sure that a correct URL is entered in [Site URL] in [Destination settings].

No library name for Microsoft SharePoint Server is specified.

Cause

No Microsoft SharePoint library is selected.

Solution

Click the [Connect] button in [Destination settings], sign in to Microsoft SharePoint, and then select a Microsoft SharePoint library from the [Library] drop-down list.

Failed to upload document(s) to Microsoft SharePoint Server.

Cause

Files could not be output to the Microsoft SharePoint Server or Microsoft SharePoint Online.

Solution

Check the following and try again.

- There is no problem with the network environment for the Microsoft SharePoint server
- There is no problem with the network environment for the computer that is in use

The folder for Microsoft SharePoint Server has not been specified.

Cause

There is no upload destination folder specified for Microsoft SharePoint Server.



Solution

Perform either of the following to specify an upload destination folder.

- Click the [Browse] button in [Destination settings] and select an upload destination folder
 - Specify an upload destination folder in the [Folder] text box in [Destination settings]
- [Before Using This Help](#)
 - [How to Use This Help](#)
 - [Cookie Policy](#)

© PFU Limited 2023



- 
-
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- Appendix


Appendix

The appendix provides additional information.

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023

- 

- 
- [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Appendix](#)>
- Authentication Client Settings for Dropbox

Authentication Client Settings for Dropbox

This section explains the Dropbox authentication client settings used with PaperStream NX Manager.

Refer to the Dropbox website.

- How to create an account
<https://help.dropbox.com/account-access/create-account>
- How to create apps/how to set permissions
<https://www.dropbox.com/developers/reference/getting-started>

Refer to the [App Console] tab.

This section explains how to configure the following settings for users with a Dropbox account.

Item	Setting Value
Client ID Client secret	Obtain from Dropbox Developers
Redirect URI	http or https:// <the IP address or host name of the computer in which PaperStream NX Manager is installed> : <the port number to communicate with PaperStream NX Manager> /NmConsole/JobEdit/GetTokenPage (*1)
Scope	account_info.read files.metadata.read files.content.write

files.content.read

*1:

Specify a URL in a format allowed by Dropbox for the redirect URI.

1. Log in to Dropbox Developers (<https://www.dropbox.com/developers>).
2. Click [Create apps].

The [Create a new app on the DBX Platform] window appears.

3. Select [Scoped access] for [1.Choose an API].
4. Select one of the following for [2.Choose the type of access you need] depending on the app you want to create.

- App folder

Only the specified folder

- Full Dropbox

All files and folders in Dropbox

HINT

If you selected [App folder] to have only the folder you specify used, a folder with the name of the folder you specify in [3.Name your app] is created under [Apps].

After you have created the specified folder, all the folders you create and all the files you save will be stored in this folder. Note that this name must be unique across the names of apps created by all the Dropbox users in the world.

5. Enter the name of the app you want to create for [3.Name your app].
6. Click the [Create app] button.

The authentication client settings configuration is complete.

7. Check the client ID and client secret in the [Settings] tab.

- App key

Displays the client ID.

- App secret

Click [Show] to display the client secret.

8. Specify the following items in the PaperStream NX Manager [\[Connector Settings\] Window](#) and click the [Save] button.
 - Client ID
 - Client secret
 - Authorized redirect URIs

9. In the Dropbox Developers menu, click [App Console].

10. Click the created app.

11. Enter "http or https:// <**the IP address or host name of the computer in which PaperStream NX Manager is installed**>: <**the port number to communicate with PaperStream NX Manager**>/NmConsole/JobEdit/GetTokenPage" for [Redirect URIs] and click the [Add] button.

12. Go to the [Permissions] tab, select the following check boxes, and then click the [Submit] button.

- o files.metadata.read
- o files.content.write
- o files.content.read

[account_info.read] is selected by default.

The scope settings configuration is complete.

HINT

If an error occurred while logging in to the service, either of the following may be incorrect.

Check each setting value.


- Scope type
- Authorized redirect URIs
- Client ID/Client secret

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



-

- 
- [Troubleshooting](#)
- [PaperStream Connector Option Help](#)>
- [Appendix](#)>
- Authentication Client Settings for Google Drive

Authentication Client Settings for Google Drive

This section explains the Google Drive authentication client settings used with PaperStream NX Manager. Refer to the Google Drive website.

<https://support.google.com/workspacemigrate/answer/9222992>

This section explains how to configure the following settings for users with a Google account.

Item	Setting Value
Client ID Client secret	Obtain from Google API Console
Redirect URI	http or https:// < the IP address or host name of the computer in which PaperStream NX Manager is installed >: < the port number to communicate with PaperStream NX Manager >/NmConsole/JobEdit/GetTokenPage (*1)
Scope	userinfo.profile openid https://www.googleapis.com/auth/drive

*1:

The redirect URI must be a URL in a format allowed by Google. Refer to the Google Drive website.

<https://developers.google.com/identity/protocols/oauth2/javascript-implicit-flow#origin-validation>

1. Log in to Google API Console (<https://console.cloud.google.com/apis/dashboard>).
2. Click [Select a project] or a name of the selected project.

The [Select a project] window appears.

- To select an existing project

Select an existing project and click the [Open] button.

- To create a new project

Click [NEW PROJECT]. In the [New Project] window, specify [Project name] and [Location], and click the [CREATE] button.

3. In the [Library] page, select [Google Drive API] and click the [Enable] button.
4. In the [Credentials] page, click [+ CREATE CREDENTIALS] and select [OAuth client ID].
5. Click the [CONFIGURE CONSENT SCREEN] button.
6. In [OAuth consent screen], select [Internal] or [External] for [User Type] according to your intended use and click the [CREATE] button.
7. In [Edit app registration], specify the following items and click the [SAVE AND CONTINUE] button.
 - App information
 - App name
 - User support email
 - Developer contact information
 - Email addresses
8. Click the [ADD OR REMOVE SCOPES] button.
9. Select the [.../auth/userinfo.profile] and [openid] check boxes.
10. Enter "https://www.googleapis.com/auth/drive" for [Manually add scopes] and click [ADD TO TABLE].
11. Make sure that the scopes are added and click the [UPDATE] button.
12. Check the scopes set in [Edit app registration] and click the [SAVE AND CONTINUE] button.
13. You do not need to set [Test users]. Click the [SAVE AND CONTINUE] button.
14. In [OAuth consent screen], click the [BACK TO DASHBOARD] button.
15. In the [Credentials] page, click [+ CREATE CREDENTIALS] and select [OAuth client ID].
16. In [Create OAuth client ID], specify the following items and click the [CREATE] button.

- Application type

Select [Web application]

- Name

- Authorized redirect URIs

Click the [+ADD URI] button and enter "http or https:// **<the IP address or host name of the computer in which PaperStream NX Manager is installed>**: **<the port number to communicate with PaperStream NX Manager>**/NmConsole/JobEdit/GetTokenPage"

17. If the [OAuth client created] window appears, check the information and click the [OK] button.

The authentication client settings configuration is complete.

18. Click on the link for the created web client under [OAuth 2.0 Client IDs] in the [Credentials] page.
19. Refer to the following items in [Client ID for Web application], specify them in the PaperStream NX Manager [\[Connector Settings\] Window](#), and click the [Save] button.

- Client ID
- Client secret
- Authorized redirect URIs

HINT

If an error occurred while logging in to the service, either of the following may be incorrect.

Check each setting value.




- Scope type
- Authorized redirect URIs
- Client ID/Client secret

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



-

- 
- 
-  [Troubleshooting](#)
- [PaperStream Connector Option Help](#) >
- [Appendix](#) >
- Authentication Client Settings for Microsoft OneDrive

Authentication Client Settings for Microsoft OneDrive

This section explains the Microsoft OneDrive authentication client settings used with PaperStream NX Manager.

This section explains how to configure the following settings for users with a Microsoft OneDrive account.

Item	Setting Value
Client ID Client secret	Obtain from Azure Portal
Redirect URI	http or https:// <i><the IP address or host name of the computer in which PaperStream NX Manager is installed></i> : <i><the port number to communicate with PaperStream NX Manager></i> /NmConsole/JobEdit/GetTokenPage (*1)
Scope	offline_access openid profile User.Read Files.ReadWrite.All

*1:

The redirect URI must be a URL in a format allowed by Microsoft. Refer to the Microsoft OneDrive

website.

<https://learn.microsoft.com/azure/active-directory/develop/reply-url>

1. Log in to Azure Portal (<https://portal.azure.com/>).
2. Select [Azure Active Directory] and click [App registrations] under [Manage] in the menu.
3. In the [App registrations] window, click [+ New registration].
4. In the [Register an application] window, specify the following items and click the [Register] button.

- o Name

Enter a name of your choice.

- o Supported account types

Select [Accounts in any organizational directory (Any Azure AD directory - Multitenant)] and personal Microsoft accounts (e.g. Skype, Xbox)].

- o Redirect URI (optional)

Select [Web] from the [Select a platform] drop-down list and enter "http or https:// **<the IP address or host name of the computer in which PaperStream NX Manager is installed>**: **<the port number to communicate with PaperStream NX Manager>**/NmConsole/JobEdit/GetTokenPage" in the text box

In the window for the created application, the application (client) ID is displayed.

5. In the window for the created application, click [Certificates & secrets] under [Manage] in the menu.
6. Click [+ New client secret].
7. In the [Add a client secret] window, add a description, set the expiration date, and click the [Add] button.

The [Certificates & secrets] window appears.

8. Click the icon next to the value for the secret ID and copy it to the clipboard.

ATTENTION

Be sure to copy the value to the clipboard in this step.

Once you navigate away from the [Certificates & secrets] window, there is no way to copy the value, which means you will have to regenerate it.

The authentication client settings configuration is complete.

9. Select [Azure Active Directory] and click [App registrations] under [Manage] in the menu.
10. Click a name of the created app and check the specified items.
 - a. Check the client ID in [Overview] in the window for the created application.
 - b. In the window for the created application, click [Authentication] under [Manage] in the menu.

You can check the redirect URI.

11. Enter the following items in the PaperStream NX Manager [\[Connector Settings\] Window](#).

- o Client ID
- o Client secret
- o Authorized redirect URIs

Next, configure the scope settings.

12. Select [Azure Active Directory] and click [App registrations] under [Manage] in the menu.
13. In the [App registrations] window, click the name of the created application.
14. In the window for the created application, click [API permissions] under [Manage] in the menu.
15. Click [Microsoft Graph] in [Configured permissions].
16. In the [Request API permissions] window, click [Delegated permissions].
17. Select the following check boxes and click the [Update permissions] button.
 - o OpenId permissions
 - offline_access
 - openid
 - profile
 - o User
 - User.Read
 - o Files
 - Files.ReadWrite.All

The scope settings configuration is complete.

HINT

If an error occurred while logging in to the service, either of the following may be incorrect.

Check each setting value.

- Scope type
- Authorized redirect URIs
- Client ID/Client secret

- [Before Using This Help](#)
- [How to Use This Help](#)
- [Cookie Policy](#)

© PFU Limited 2023



•